

# MBS REALbasic Audio Plugin Documentation

Christian Schmitz

January 17, 2011

## 0.1 Introduction

This is the PDF version of the documentation for the REALbasic Plug-in from Monkeybread Software Germany. Plugin part: MBS REALbasic Audio Plugin

## 0.2 Content

- 1 List of all topics 3
- 2 All items in this plugin 11
- 4 List of all classes 111

# Chapter 1

## List of Topics

• 2 Audio	11
– 2.1 class PortAudioStreamBufferedMBS	11
* 2.1.1 AddAudio(Data as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean	11
* 2.1.1 AddAudioStereo(Data1 as memoryblock, Data2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean	12
* 2.1.1 AddFloatAudio(FloatData as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean	13
* 2.1.1 AddFloatAudioStereo(FloatData1 as memoryblock, FloatData2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean	14
* 2.1.1 FreeSpace as integer	15
* 2.1.1 HasFreeSpace as boolean	15
* 2.1.1 OpenDefaultStream(numOutputChannels as integer, sampleRate as double) as integer	15
* 2.1.1 OpenStream(outputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer	16
* 2.1.1 PlayAudio(Data as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean	17
* 2.1.1 PlayAudioStereo(Data1 as memoryblock, Data2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean	18
* 2.1.1 PlayFloatAudio(FloatData as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean	19
* 2.1.1 PlayFloatAudioStereo(FloatData1 as memoryblock, FloatData2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean	20

* 2.1.2 HadUnderflow as Boolean	21
* 2.1.2 NoUnderflow as Boolean	21
* 2.1.2 OutputPosition as Double	21
* 2.1.2 OutputPositionRelative as Double	22
* 2.1.3 Finished	22
– 2.7 class PortAudioStreamBaseMBS	43
* 2.7.1 Abort as integer	43
* 2.7.1 Close as integer	43
* 2.7.1 CPUload as double	43
* 2.7.1 HostError as PortAudioHostErrorInfoMBS	44
* 2.7.1 Info as PortAudioStreamInfoMBS	44
* 2.7.1 IsStreamActive as integer	45
* 2.7.1 IsStreamStopped as integer	45
* 2.7.1 Start as integer	45
* 2.7.1 Stop as integer	46
* 2.7.1 Time as double	46
* 2.7.1 UseSafeThreading as boolean	46
– 2.2 class PortAudioStreamMBS	22
* 2.2.1 OpenDefaultStream(numInputChannels as integer, numOutputChannels as integer, sampleFormat as integer, sampleRate as double, framesPerBuffer as integer, Flags as integer) as integer	23
* 2.2.1 OpenStream(inputParameters as PortAudioStreamParametersMBS, outputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer	24
* 2.2.1 Read(buffer as memoryblock, frameCount as integer) as integer	25
* 2.2.1 ReadAvailable as integer	26
* 2.2.1 Write(buffer as memoryblock, frameCount as integer) as integer	26
* 2.2.1 WriteAvailable as integer	27
* 2.2.2 Callback(InputBuffer as memoryblock, outputBuffer as memoryblock, FrameCount as integer, inputBufferAdcTime as double, currentTime as double, outputBufferDacTime as double, statusFlags as integer) as integer	27
* 2.2.2 Finished	29
– 2.3 class PortAudioStreamInfoMBS	29
* 2.3.1 InputLatency as Double	30
* 2.3.1 OutputLatency as Double	30
* 2.3.1 SampleRate as Double	30
– 2.6 class PortAudioHostApiInfoMBS	40
* 2.6.1 defaultInputDevice as Integer	40
* 2.6.1 defaultOutputDevice as Integer	41
* 2.6.1 deviceCount as Integer	41
* 2.6.1 Index as Integer	41

* 2.6.1 Name as String	42
* 2.6.1 Type as Integer	42
– 2.4 class PortAudioHostErrorInfoMBS	31
* 2.4.1 ErrorCode as Integer	31
* 2.4.1 ErrorText as String	31
* 2.4.1 HostApiType as Integer	32
– 2.5 class PortAudioMBS	32
* 2.5.1 CountDevices as integer	32
* 2.5.1 DefaultHostApiIndexd as integer	33
* 2.5.1 DefaultInputDeviceID as integer	34
* 2.5.1 DefaultOutputDeviceID as integer	34
* 2.5.1 DeviceInfo(DeviceIndex as integer) as PortAudioDeviceInfoMBS	35
* 2.5.1 ErrorText(ErrorNumber as integer) as string	35
* 2.5.1 GetSampleSize(Format as integer) as integer	35
* 2.5.1 HostApiCount as integer	35
* 2.5.1 HostApiDeviceIndexToDeviceIndex(hostApiIndex as integer, hostApiDeviceIndex as integer) as integer	36
* 2.5.1 HostApiInfo(hostApiIndex as integer) as PortAudioHostApiInfoMBS	36
* 2.5.1 HostApiTypeIdToHostApiIndex(type as integer) as integer	37
* 2.5.1 HostError as PortAudioHostErrorInfoMBS	37
* 2.5.1 IsFormatSupported(input as PortAudioStreamParametersMBS, output as PortAudioStreamParametersMBS, sampleRate as double) as integer	38
* 2.5.1 SampleSize(theFormat as integer) as integer	38
* 2.5.1 Sleep(msec as integer)	39
* 2.5.1 Version as integer	40
* 2.5.1 VersionText as String	40
– 2.10 class PortAudioDeviceInfoMBS	55
* 2.10.1 DefaultHighInputLatency as Double	55
* 2.10.1 DefaultHighOutputLatency as Double	55
* 2.10.1 DefaultLowInputLatency as Double	56
* 2.10.1 DefaultLowOutputLatency as Double	56
* 2.10.1 DefaultSampleRate as Double	56
* 2.10.1 HostApiIndex as Integer	56
* 2.10.1 Index as Integer	57
* 2.10.1 MaxInputChannels as integer	57
* 2.10.1 MaxOutputChannels as integer	57
* 2.10.1 Name as String	58
– 2.8 class PortAudioStreamRecorderMBS	47
* 2.8.1 Constructor(BufferSize as integer)	47
* 2.8.1 Flush	48
* 2.8.1 OpenDefaultStream(numInputChannels as integer, sampleRate as double) as integer	48

* 2.8.1 OpenStream(inputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer	48
* 2.8.1 ReadFrames(mem as memoryblock, SizeInBytes as integer) as integer	50
* 2.8.1 ResizeBuffer(BufferSize as integer)	50
* 2.8.2 Buffer as Memoryblock	51
* 2.8.2 BufferReadIndex as Integer	51
* 2.8.2 BufferSize as Integer	51
* 2.8.2 BufferWriteIndex as Integer	52
* 2.8.2 FramesAvailable as Integer	52
* 2.8.2 NumInputChannels as Integer	52
– 2.9 class PortAudioStreamParametersMBS	53
* 2.9.1 ChannelCount as Integer	53
* 2.9.1 Device as Integer	53
* 2.9.1 SampleFormat as Integer	54
* 2.9.1 SuggestedLatency as Double	54
• 3 MIDI	59
– 3.1 class PortMidiStreamMBS	59
* 3.1.1 Abort as integer	59
* 3.1.1 Close	60
* 3.1.1 ErrorText(ErrorNumber as integer) as string	60
* 3.1.1 OpenInput(DeviceID as integer, Buffersize as integer) as integer	60
* 3.1.1 OpenOutput(DeviceID as integer, Buffersize as integer, Latency as integer) as integer	61
* 3.1.1 Poll as integer	61
* 3.1.1 Read(byref data as PortMidiEventMBS) as integer	62
* 3.1.1 SetChannelMask(mask as integer) as integer	62
* 3.1.1 SetFilter(filters as integer) as integer	63
* 3.1.1 Write(data as PortMidiEventMBS) as integer	63
* 3.1.1 WriteShort(When as integer, message as integer) as integer	64
* 3.1.1 WriteSysEx(When as integer, message as memoryblock, offset as integer) as integer	64
* 3.1.1 WriteSysEx(When as integer, message as string) as integer	65
* 3.1.2 ChannelMask as Integer	65
* 3.1.2 Filters as Integer	65
* 3.1.3 FilterActive = & h4000	66
* 3.1.3 FilterAftertouch = & h6000000	66
* 3.1.3 FilterChannelAftertouch = & h20000000	66
* 3.1.3 FilterClock & h1D00	66
* 3.1.3 FilterControl & h8000000	67
* 3.1.3 FilterFD = & h2000	67
* 3.1.3 FilterMTC = 2	67
* 3.1.3 FilterNote = & h3000000	67

* 3.1.3 FilterPitchBend = & h40000000	68
* 3.1.3 FilterPlay = & h400	68
* 3.1.3 FilterPolyAftertouch = & h4000000	68
* 3.1.3 FilterProgram = & h10000000	68
* 3.1.3 FilterRealTime = & hFF01	69
* 3.1.3 FilterReset = & h8000	69
* 3.1.3 FilterSongPosition = 4	69
* 3.1.3 FilterSongSelect = 8	69
* 3.1.3 FilterSysEx = 1	70
* 3.1.3 FilterSystemCommon = & h4E	70
* 3.1.3 FilterTick = & h200	70
* 3.1.3 FilterTune = & h40	70
* 3.1.3 FilterUndefined = & h2000	71
– 3.3 class PortMidiMBS	72
* 3.3.1 CountDevices as integer	73
* 3.3.1 DefaultInputDeviceID as integer	73
* 3.3.1 DefaultOutputDeviceID as integer	74
* 3.3.1 DeviceInfo(DeviceID as integer) as PortMidiDeviceInfoMBS	75
* 3.3.1 ErrorText(ErrorNumber as integer) as string	75
* 3.3.1 ReInitialize as integer	75
* 3.3.2 pmBadData = -9994	76
* 3.3.2 pmBadPtr = -9995	76
* 3.3.2 pmBufferMaxSize = -9992	76
* 3.3.2 pmBufferOverflow = -9996	77
* 3.3.2 pmBufferTooSmall = -9997	77
* 3.3.2 pmHostError = -10000	77
* 3.3.2 pmInsufficientMemory = -9998	77
* 3.3.2 pmInternalError = -9993	77
* 3.3.2 pmInvalidDeviceId = -9999	78
* 3.3.2 pmNoDevice = -1	78
* 3.3.2 pmNoError = 0	78
– 3.2 class PortMidiDeviceInfoMBS	71
* 3.2.1 HasInput as Boolean	71
* 3.2.1 HasOutput as Boolean	71
* 3.2.1 InterfaceName as String	72
* 3.2.1 Name as String	72
– 3.4 class PortMidiEventMBS	78
* 3.4.1 Set(status as integer, data1 as integer, data2 as integer)	79
* 3.4.1 SetRaw(data0 as integer, data1 as integer, data2 as integer, data3 as integer)	79
* 3.4.2 Data1 as Integer	79
* 3.4.2 Data2 as Integer	79

* 3.4.2 RawData0 as Integer	80
* 3.4.2 RawData1 as Integer	80
* 3.4.2 RawData2 as Integer	80
* 3.4.2 RawData3 as Integer	81
* 3.4.2 RawMessage as Integer	81
* 3.4.2 Status as Integer	81
* 3.4.2 When as Integer	81
– 3.5 class WindowsMidiOutputMBS	82
* 3.5.1 Close	82
* 3.5.1 Open(DeviceID as integer)	82
* 3.5.1 OpenDefault	83
* 3.5.1 OutputErrorText(errorcode as integer) as string	83
* 3.5.1 Reset	83
* 3.5.1 SendData(data as memoryblock, size as integer)	83
* 3.5.1 SendData(data as string)	84
* 3.5.1 SendMessage(message as integer)	85
* 3.5.1 SendMessage(status as integer, data1 as integer, data2 as integer)	85
* 3.5.1 Volume as integer	86
* 3.5.2 DeviceClose	87
* 3.5.2 DeviceDataSent	87
* 3.5.2 DeviceOpen	87
* 3.5.2 DevicePositionCallback	87
– 3.9 class WindowsMidiOutputInfoMBS	100
* 3.9.1 ChannelMask as Integer	100
* 3.9.1 DriverVersion as Integer	100
* 3.9.1 Flags as Integer	101
* 3.9.1 ManufacturerID as Integer	101
* 3.9.1 Name as String	101
* 3.9.1 Notes as Integer	102
* 3.9.1 ProductID as Integer	102
* 3.9.1 Technology as Integer	102
* 3.9.1 Voices as Integer	103
* 3.9.1 Volume as Boolean	103
* 3.9.1 VolumeStereo as Boolean	103
– 3.6 class WindowsMidiStreamMBS	88
* 3.6.1 Close	88
* 3.6.1 Open(DeviceID as integer)	88
* 3.6.1 Pause	88
* 3.6.1 PositionBytes as integer	89
* 3.6.1 PositionMS as integer	89
* 3.6.1 PositionSamples as integer	89

* 3.6.1 PositionTicks as integer	89
* 3.6.1 Restart	90
* 3.6.1 SendMessage(message as integer)	90
* 3.6.1 SendMessage(status as integer, data1 as integer, data2 as integer)	91
* 3.6.1 Stop	91
* 3.6.1 Tempo as integer	91
* 3.6.1 TimeDiv as integer	92
* 3.6.1 Volume as integer	92
* 3.6.2 Handle as Integer	93
* 3.6.2 Lasterror as Integer	93
– 3.7 class WindowsMidiInputMBS	93
* 3.7.1 Close	94
* 3.7.1 Idle	94
* 3.7.1 InputErrorText(errorcode as integer) as string	94
* 3.7.1 Open(DeviceID as integer, BufferSize as integer)	95
* 3.7.1 Reset	95
* 3.7.1 Start	95
* 3.7.1 Stop	96
* 3.7.2 DeviceClose	96
* 3.7.2 DeviceData(timestamp as integer, status as integer, data1 as integer, data2 as integer)	96
* 3.7.2 DeviceError(timestamp as integer, status as integer, data1 as integer, data2 as integer)	97
* 3.7.2 DeviceLongData(timestamp as integer, data as string)	97
* 3.7.2 DeviceLongError(timestamp as integer, data as string)	97
* 3.7.2 DeviceOpen	98
– 3.8 class WindowsMidiInputInfoMBS	98
* 3.8.1 DriverVersion as Integer	98
* 3.8.1 Flags as Integer	98
* 3.8.1 ManufacturerID as Integer	99
* 3.8.1 Name as String	99
* 3.8.1 ProductID as Integer	99
– 3.10 class WindowsMidiMBS	104
* 3.10.1 Connect(output as WindowsMidiOutputMBS)	105
* 3.10.1 DataLost as integer	105
* 3.10.1 Disconnect(output as WindowsMidiOutputMBS)	106
* 3.10.1 EventsLost as integer	106
* 3.10.1 Idle	106
* 3.10.1 InputDevice(index as integer) as WindowsMidiInputInfoMBS	107
* 3.10.1 NumberOfMidiInputDevices as integer	107
* 3.10.1 NumberOfMidiOutputDevices as integer	108

* 3.10.1 OutputDevice(index as integer) as WindowsMidiOutputInfoMBS	108
* 3.10.2 Handle as Integer	109
* 3.10.2 Lasterror as Integer	109

# Chapter 2

## Audio

### 2.1 class PortAudioStreamBufferedMBS

class PortAudioStreamBufferedMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A portaudio stream class to use an internal buffer to feed its callback.

**Notes:**

Currently this class allows you to add 200 buffers to the internal playlist. The buffer size is not limited. FreeSpace returns you the number of buffers you have currently. Buffers are freed after they are played. Subclass of the PortAudioStreamBaseMBS class.

#### 2.1.1 Methods

**AddAudio(Data as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue.

**Notes:**

Data: a memoryblock with the sound data

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

You need to set numOutputChannels to 1 or 2 when opening the stream. For 2 channels, sound data must be interleaved.

Values for bitsize:

7	signed byte
8	unsigned byte
15	signed short
16	unsigned short
24	unsigned medium
31	signed integer
32	unsigned integer

This method copies the data to the internal queue. It returns directly.

If ClearBuffers is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

Returns true on success and false on failure (e.g. out of memory).

**AddAudioStereo(Data1 as memoryblock, Data2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue.

**Notes:**

This is a special version of AddAudio which takes samples from both memoryblocks and interleaves them.

Data1: a memoryblock with the sound data

Data2: a memoryblock with the sound data

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

The stream must use 2 channels for this method to work correctly.

Values for bitsize:

- 7 signed byte
- 8 unsigned byte
- 15 signed short
- 16 unsigned short
- 24 unsigned medium
- 31 signed integer
- 32 unsigned integer

This method copies the data to the internal queue. It returns directly.

If ClearBuffers is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

Returns true on success and false on failure (e.g. out of memory).

**AddFloatAudio(FloatData as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue.

**Notes:**

FloatData: a memoryblock with the sound data filled with single values.

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

You need to set numOutputChannels to 1 or 2 when opening the stream. For 2 channels, sound data must be interleaved.

The samples are stored in 32bit float values (memoryblock.SingleValue)

This method copies the data to the internal queue. It returns directly.

If ClearBuffers is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

Returns true on success and false on failure (e.g. out of memory).

**AddFloatAudioStereo(FloatData1 as memoryblock, FloatData2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue.

**Notes:**

This is a special version of AddFloatAudio which takes samples from both memoryblocks and interleaves them.

FloatData1: a memoryblock with the sound data filled with single values.

FloatData2: a memoryblock with the sound data filled with single values.

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

The samples are stored in 32bit float values (memoryblock.SingleValue)

This method copies the data to the internal queue. It returns directly.

The stream must use 2 channels for this method to work correctly.

If `ClearBuffers` is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

Returns true on success and false on failure (e.g. out of memory).

### **FreeSpace as integer**

method from class `PortAudioStreamBufferedMBS`, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns the number of buffer entries available in the queue.

**Notes:** The size of the buffers is not limited except your available memory.

### **HasFreeSpace as boolean**

method from class `PortAudioStreamBufferedMBS`, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns true if the internal sound buffer has free space.

**Notes:**

Returns true if `freespace` returns a value greater than zero.

This function was named `IsQueueEmpty` in plugin version 7.4.

### **OpenDefaultStream(numOutputChannels as integer, sampleRate as double) as integer**

method from class `PortAudioStreamBufferedMBS`, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A simplified version of `OpenStream()` that opens the default input and/or output devices.

**Notes:**

`Sampleformat` is always 32bit float in this class. All data you add the queue is converted to float internally.

`numOutputChannels`: The number of channels of sound to be delivered to the stream callback or passed to `Write`. It can range from 1 to the value of `maxOutputChannels` in the `PortAudioDeviceInfoMBS` object for the default output device. If 0 the stream is opened as an output-only stream.

`sampleRate`: Same as `OpenStream` parameter of the same name.

Returns an error code.

**OpenStream(outputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer**

method from class `PortAudioStreamBufferedMBS`, `Audio`, `MBS REALbasic Audio Plugin (PortAudio)`, Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Opens a stream for either input, output or both.

**Notes:**

`Sampleformat` is always 32bit float in this class. All data you add the queue is converted to float internally.

`outputParameters`: A object that describes the output parameters used by the opened stream. See `PortAudioStreamParametersMBS` for a description of these parameters.

`sampleRate`: The desired `sampleRate`. For full-duplex streams it is the sample rate for both input and output

`framesPerBuffer`: The number of frames passed to the stream callback function, or the preferred block granularity for a blocking read/write stream. The special value `paFramesPerBufferUnspecified` (0) may be used to request that the stream callback will receive an optimal (and possibly varying) number of frames based on host requirements and the requested latency settings.

Note: With some host APIs, the use of non-zero `framesPerBuffer` for a callback stream may introduce an additional layer of buffering which could introduce additional latency. `PortAudio` guarantees that the additional latency will be kept to the theoretical minimum however, it is strongly recommended that a non-zero `framesPerBuffer` value only be used when your algorithm requires a fixed number of frames per stream callback.

```
const paFramesPerBufferUnspecified=0
```

streamFlags: Flags which modify the behaviour of the streaming process. This parameter may contain a combination of flags ORed together. Some flags may only be relevant to certain buffer formats.

const paNoFlag	= 0	no flags
const paClipOff	= 1	Disable default clipping of out of range samples.
const paDitherOff	= 2	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the paFramesPerBufferUnspecified (0) framesPerBuffer parameter. Using this flag incorrectly results in a paInvalidFlag error being returned from OpenStream and OpenDefaultStream.
const paNeverDropInput	= 4	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the paFramesPerBufferUnspecified (0) framesPerBuffer parameter. Using this flag incorrectly results in a paInvalidFlag error being returned from OpenStream and OpenDefaultStream.
const paPrimeOutputBuffersUsingStreamCallback	= 8	Call the stream callback to fill initial output buffers, rather than the default behavior of priming the buffers with zeros (silence). This flag has no effect for input-only and blocking read/write streams.

Upon success OpenStream() returns paNoError and places a pointer to a valid PaStream in the stream argument. The stream is inactive (stopped).

If a call to OpenStream() fails, a non-zero error code is returned (see PaError for possible error codes) and the value of stream is invalid.

**PlayAudio(Data as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue and starts playback.

**Notes:**

Data: a memoryblock with the sound data

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

You need to set numOutputChannels to 1 or 2 when opening the stream. For 2 channels, sound data must be interleaved.

Values for bitsize:

7	signed byte
8	unsigned byte
15	signed short
16	unsigned short
24	unsigned medium
31	signed integer
32	unsigned integer

This method copies the data to the internal queue. It returns directly.

If `ClearBuffers` is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

**PlayAudioStereo(Data1 as memoryblock, Data2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, BitSize as integer=16, ClearBuffers as boolean=false) as boolean**

method from class `PortAudioStreamBufferedMBS`, `Audio`, `MBS REALbasic Audio Plugin (PortAudio)`, Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue and starts playback.

**Notes:**

This is a special version of `AddAudio` which takes samples from both memoryblocks and interleaves them.

`Data1`: a memoryblock with the sound data

`Data2`: a memoryblock with the sound data

`offsetBytes`: the number of the bytes to start playing (0=first)

`countBytes`: the number of bytes to play from offset. If `countBytes` is zero, the memoryblock's size property is used.

The stream must use 2 channels for this method to work correctly.

Values for bitsize:

7	signed byte
8	unsigned byte
15	signed short
16	unsigned short
24	unsigned medium
31	signed integer
32	unsigned integer

This method copies the data to the internal queue. It returns directly.

If `ClearBuffers` is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick. #

**PlayFloatAudio(FloatData as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue and starts playback.

**Notes:**

`FloatData`: a memoryblock with the sound data filled with single values.

`offsetBytes`: the number of the bytes to start playing (0=first)

`countBytes`: the number of bytes to play from offset. If `countBytes` is zero, the memoryblock's size property is used.

You need to set `numOutputChannels` to 1 or 2 when opening the stream. For 2 channels, sound data must be interleaved.

The samples are stored in 32bit float values (`memoryblock.SingleValue`)

This method copies the data to the internal queue. It returns directly.

If `ClearBuffers` is true, the buffer list will be cleared before this new data is added. This allows to have the

next minute in the buffers and still do a change in the stream quick.##

**PlayFloatAudioStereo(FloatData1 as memoryblock, FloatData2 as memoryblock, offsetBytes as integer=0, countBytes as integer=0, ClearBuffers as boolean=false) as boolean**

method from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Adds audio to the queue and starts playback.

**Notes:**

This is a special version of AddFloatAudio which takes samples from both memoryblocks and interleaves them.

FloatData1: a memoryblock with the sound data filled with single values.

FloatData2: a memoryblock with the sound data filled with single values.

offsetBytes: the number of the bytes to start playing (0=first)

countBytes: the number of bytes to play from offset. If countBytes is zero, the memoryblock's size property is used.

The samples are stored in 32bit float values (memoryblock.SingleValue)

This method copies the data to the internal queue. It returns directly.

The stream must use 2 channels for this method to work correctly.

If ClearBuffers is true, the buffer list will be cleared before this new data is added. This allows to have the next minute in the buffers and still do a change in the stream quick.

## 2.1.2 Properties

### HadUnderflow as Boolean

property from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.5, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A flag set if a data underflow was found while NoUnderflow is true.

**Notes:**

You may want to set this to false after your application recovered from a data underflow.  
(Read and Write property)

### NoUnderflow as Boolean

property from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.5, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Whether underflows should be prevented.

**Notes:**

If no audio data is there and NoUnderflow=true, the flag HadUnderflow is set to true and 0 values (Silence) is played.

Switching from sound to no sound and back may add some noise.  
(Read and Write property)

### OutputPosition as Double

property from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The current position in the playing stream.

**Notes:**

May point between samples.  
(Read only property)

### OutputPositionRelative as Double

property from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The current position in the playing buffer.

**Notes:**

May point between samples.

Will reset to 0 when a new buffer is used.

(Read only property)

### 2.1.3 Events

#### Finished

event from class PortAudioStreamBufferedMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** This event is implemented by PortAudio clients.

**Notes:**

Once registered they are called when the stream becomes inactive (ie once a call to Stop() will not block). A stream will become inactive after the stream callback returns non-zero, or when Stop or Abort is called. For a stream providing audio output, if the stream callback returns paComplete, or Stop is called, the stream finished callback will not be called until all generated sample data has been played.

## 2.2 class PortAudioStreamMBS

### class PortAudioStreamMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A single PortAudioStreamMBS can provide multiple channels of real-time streaming audio input and output to a client application.

**Notes:**

A stream provides access to audio hardware represented by one or more devices. Depending on the underlying Host API, it may be possible to open multiple streams using the same device, however this behavior is implementation defined. Portable applications should assume that a device may be simultaneously used by at most one PortAudioStreamMBS.

Subclass of the PortAudioStreamBaseMBS class.

### 2.2.1 Methods

**OpenDefaultStream(numInputChannels as integer, numOutputChannels as integer, sampleFormat as integer, sampleRate as double, framesPerBuffer as integer, Flags as integer) as integer**

method from class PortAudioStreamMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A simplified version of OpenStream() that opens the default input and/or output devices.

**Notes:**

**numInputChannels:** The number of channels of sound that will be supplied to the stream callback or returned by ReadStream. It can range from 1 to the value of maxInputChannels in the PaDeviceInfo record for the default input device. If 0 the stream is opened as an output-only stream.

**numOutputChannels:** The number of channels of sound to be delivered to the stream callback or passed to Write. It can range from 1 to the value of maxOutputChannels in the PaDeviceInfo record for the default output device. If 0 the stream is opened as an output-only stream.

**sampleFormat:** The sample format of both the input and output buffers provided to the callback or passed to and from Read and Write.

sampleFormat may be any of the formats described by the PaSampleFormat enumeration.

**sampleRate:** Same as OpenStream parameter of the same name.

**framesPerBuffer:** Same as OpenStream parameter of the same name.

constants for the flags value:

Returns an error code.

<code>const paNoFlag</code>	= 0	no flags
<code>const paClipOff</code>	= 1	Disable default clipping of out of range samples.
<code>const paDitherOff</code>	= 2	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the <code>paFramesPerBufferUnspecified</code> (0) <code>framesPerBuffer</code> parameter. Using this flag incorrectly results in a <code>paInvalidFlag</code> error being returned from <code>OpenStream</code> and <code>OpenDefaultStream</code> .
<code>const paNeverDropInput</code>	= 4	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the <code>paFramesPerBufferUnspecified</code> (0) <code>framesPerBuffer</code> parameter. Using this flag incorrectly results in a <code>paInvalidFlag</code> error being returned from <code>OpenStream</code> and <code>OpenDefaultStream</code> .
<code>const paPrimeOutputBuffersUsingStreamCallback</code>	= 8	Call the stream callback to fill initial output buffers, rather than the default behavior of priming the buffers with zeros (silence). This flag has no effect for input-only and blocking read/write streams.

**OpenStream(inputParameters as PortAudioStreamParametersMBS, outputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer**

method from class `PortAudioStreamMBS`, `Audio`, `MBS REALbasic Audio Plugin (PortAudio)`, `Plugin` version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Opens a stream for either input, output or both.

**Notes:**

`inputParameters`: A object that describes the input parameters used by the opened stream. See `PortAudioStreamParametersMBS` for a description of these parameters. `inputParameters` must be `nil` for output-only streams.

`outputParameters`: A object that describes the output parameters used by the opened stream. See `PortAudioStreamParametersMBS` for a description of these parameters. `outputParameters` must be `nil` for input-only streams.

`sampleRate`: The desired `sampleRate`. For full-duplex streams it is the sample rate for both input and output

`framesPerBuffer`: The number of frames passed to the stream callback function, or the preferred block granularity for a blocking read/write stream. The special value `paFramesPerBufferUnspecified` (0) may be used to request that the stream callback will receive an optimal (and possibly varying) number of frames based on host requirements and the requested latency settings.

Note: With some host APIs, the use of non-zero `framesPerBuffer` for a callback stream may introduce an additional layer of buffering which could introduce additional latency. `PortAudio` guarantees that the additional latency will be kept to the theoretical minimum however, it is strongly recommended that a non-zero `framesPerBuffer` value only be used when your algorithm requires a fixed number of frames per stream callback.

`const paFramesPerBufferUnspecified=0`

streamFlags: Flags which modify the behaviour of the streaming process. This parameter may contain a combination of flags ORed together. Some flags may only be relevant to certain buffer formats.

const paNoFlag	= 0	no flags
const paClipOff	= 1	Disable default clipping of out of range samples.
const paDitherOff	= 2	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the paFramesPerBufferUnspecified (0) framesPerBuffer parameter. Using this flag incorrectly results in a paInvalidFlag error being returned from OpenStream and OpenDefaultStream.
const paNeverDropInput	= 4	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the paFramesPerBufferUnspecified (0) framesPerBuffer parameter. Using this flag incorrectly results in a paInvalidFlag error being returned from OpenStream and OpenDefaultStream.
const paPrimeOutputBuffersUsingStreamCallback	= 8	Call the stream callback to fill initial output buffers, rather than the default behavior of priming the buffers with zeros (silence). This flag has no effect for input-only and blocking read/write streams.

If this the callback event is left empty the stream will be opened in 'blocking read/write' mode. In blocking mode, the client can receive sample data using Read and write sample data using Write, the number of samples that may be read or written without blocking is returned by ReadAvailable and WriteAvailable respectively.

Upon success OpenStream() returns paNoError and places a pointer to a valid PaStream in the stream argument. The stream is inactive (stopped).

If a call to OpenStream() fails, a non-zero error code is returned (see PaError for possible error codes) and the value of stream is invalid.

### Read(buffer as memoryblock, frameCount as integer) as integer

method from class PortAudioStreamMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Read samples from an input stream.

**Notes:**

The function doesn't return until the entire buffer has been filled - this may involve waiting for the operating system to supply the data.

**buffer:** A buffer of sample frames. The buffer contains samples in the format specified by the `input.sampleFormat` field used to open the stream, and the number of channels specified by `input.numChannels`. If non-interleaved samples were requested, `buffer` is a pointer to the first element of an array of non-interleaved buffer pointers, one for each channel.

**frameCount:** The number of frames to be read into `buffer`. This parameter is not constrained to a specific range, however high performance applications will want to match this parameter to the `framesPerBuffer` parameter used when opening the stream.

Returns on success `PaNoError` will be returned, or `PaInputOverflowed` (-9981) if input data was discarded by `PortAudio` after the previous call and before this call.

### **ReadAvailable as integer**

method from class `PortAudioStreamMBS`, `Audio`, `MBS REALbasic Audio Plugin (PortAudio)`, Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the number of frames that can be read from the stream without waiting.

**Notes:** Returns a non-negative value representing the maximum number of frames that can be read from the stream without blocking or busy waiting or, a `PaErrorCode` (which are always negative) if `PortAudio` is not initialized or an error is encountered.

### **Write(buffer as memoryblock, frameCount as integer) as integer**

method from class `PortAudioStreamMBS`, `Audio`, `MBS REALbasic Audio Plugin (PortAudio)`, Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Write samples to an output stream.

**Notes:**

This function doesn't return until the entire buffer has been consumed - this may involve waiting for the operating system to consume the data.

**buffer:** A buffer of sample frames. The buffer contains samples in the format specified by the `outputParameters.sampleFormat` field used to open the stream, and the number of channels specified by `outputParameters.numChannels`. If non-interleaved samples were requested, `buffer` is a pointer to the first element of an array of non-interleaved buffer pointers, one for each channel.

frameCount: The number of frames to be written from buffer. This parameter is not constrained to a specific range, however high performance applications will want to match this parameter to the framesPerBuffer parameter used when opening the stream.

On success PaNoError (0) will be returned, or paOutputUnderflowed (-9980) if additional output data was inserted after the previous call and before this call.

### WriteAvailable as integer

method from class PortAudioStreamMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the number of frames that can be written to the stream without waiting.

**Notes:** Returns a non-negative value representing the maximum number of frames that can be written to the stream without blocking or busy waiting or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

## 2.2.2 Events

**Callback(InputBuffer as memoryblock, outputBuffer as memoryblock, FrameCount as integer, inputBufferAdcTime as double, currentTime as double, outputBufferDacTime as double, statusFlags as integer) as integer**

event from class PortAudioStreamMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The event called when new data is needed or received.

**Notes:**

This event is implemented by PortAudio clients. They consume, process or generate audio in response to requests from an active PortAudio stream.

InputBuffer and outputBuffer are arrays of interleaved samples, the format, packing and number of channels used by the buffers are determined by parameters to OpenStream().

frameCount: The number of sample frames to be processed by the stream callback.

inputBufferAdcTime, currentTimeTiming and outputBufferDacTime: The time in seconds when the first

sample of the input buffer was received at the audio input, the time in seconds when the first sample of the output buffer will begin being played at the audio output, and the time in seconds when the stream callback was called.

`statusFlags`: Flags indicating whether input and/or output buffers have been inserted or will be dropped to overcome underflow or overflow conditions.

Returns the stream callback should return one of the values in the `PaStreamCallbackResult` enumeration. To ensure that the callback continues to be called, it should return `paContinue` (0). Either `paComplete` or `paAbort` can be returned to finish stream processing, after either of these values is returned the callback will not be called again. If `paAbort` is returned the stream will finish as soon as possible. If `paComplete` is returned, the stream will continue until all buffers generated by the callback have been played.

This may be useful in applications such as soundfile players where a specific duration of output is required. However, it is not necessary to utilise this mechanism as `Stop()`, `Abort()` or `Close()` can also be used to stop the stream. The callback must always fill the entire output buffer irrespective of its return value.

With the exception of `CpuLoad()` it is not permissible to call PortAudio API functions from within the stream callback.

Flag bit constants for the `statusFlags` to `Callback`:

`paInputUnderflow` = 1

In a stream opened with `paFramesPerBufferUnspecified`, indicates that input data is all silence (zeros) because no real data is available. In a stream opened without `paFramesPerBufferUnspecified`, it indicates that one or more zero samples have been inserted into the input buffer to compensate for an input underflow.

`paInputOverflow` = 2

In a stream opened with `paFramesPerBufferUnspecified`, indicates that data prior to the first sample of the input buffer was discarded due to an overflow, possibly because the stream callback is using too much CPU time. Otherwise indicates that data prior to one or more samples in the input buffer was discarded.

`paOutputUnderflow` = 4

Indicates that output data (or a gap) was inserted, possibly because the stream callback is using too much CPU time.

`paOutputOverflow` = 8

Indicates that output data will be discarded because no room is available.

```
paPrimingOutput = 16
```

Some of all of the output data will be used to prime the stream, input data may be zero.

Allowable return values for the callback: (PaStreamCallbackResult)

```
const paContinue    = 0
const paComplete    = 1
const paAbort       = 2
```

### Finished

event from class PortAudioStreamMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** This event is implemented by PortAudio clients.

**Notes:**

Once registered they are called when the stream becomes inactive (ie once a call to Stop() will not block). A stream will become inactive after the stream callback returns non-zero, or when Stop or Abort is called. For a stream providing audio output, if the stream callback returns paComplete, or Stop is called, the stream finished callback will not be called until all generated sample data has been played.

## 2.3 class PortAudioStreamInfoMBS

### class PortAudioStreamInfoMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class to hold time information of the current stream.

### 2.3.1 Properties

#### InputLatency as Double

property from class PortAudioStreamInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The input latency of the stream in seconds.

**Notes:**

This value provides the most accurate estimate of input latency available to the implementation. It may differ significantly from the suggestedLatency value passed to OpenStream().

The value of this field will be zero (0.) for output-only streams.

(Read only property)

#### OutputLatency as Double

property from class PortAudioStreamInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The output latency of the stream in seconds.

**Notes:**

This value provides the most accurate estimate of output latency available to the implementation. It may differ significantly from the suggestedLatency value passed to OpenStream().

The value of this field will be zero (0.) for input-only streams.

(Read only property)

#### SampleRate as Double

property from class PortAudioStreamInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The sample rate of the stream in Hertz (samples per second).

**Notes:**

In cases where the hardware sample rate is inaccurate and PortAudio is aware of it, the value of this field may be different from the sampleRate parameter passed to OpenStream(). If information about the actual hardware sample rate is not available, this field will have the same value as the sampleRate parameter passed

to `OpenStream()`.  
(Read only property)

## 2.4 class PortAudioHostErrorInfoMBS

### class PortAudioHostErrorInfoMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class used to return information about a host error condition.

### 2.4.1 Properties

#### ErrorCode as Integer

property from class PortAudioHostErrorInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** the error code returned.

**Notes:** (Read only property)

#### ErrorText as String

property from class PortAudioHostErrorInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A textual description of the error if available, otherwise a zero-length string.

**Notes:** (Read only property)

### HostApiType as Integer

property from class PortAudioHostErrorInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The host API which returned the error code.

**Notes:** (Read only property)

## 2.5 class PortAudioMBS

### class PortAudioMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class to run the opensource PortAudio library in Realbasic.

**Notes:**

Constants for error codes:

Initialization and Termination of the PortAudio library are done in background automatically.

### 2.5.1 Methods

#### CountDevices as integer

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the number of available devices.

**Notes:**

The number of available devices may be zero.

Returns a non-negative value indicating the number of available devices or, a PaErrorCode (which are always

paNoError	= 0
Plugin parameter error	= -1
paNotInitialized	= -10000,
paUnanticipatedHostError	= -9999
paInvalidChannelCount	= -9998
paInvalidSampleRate	= -9997
paInvalidDevice	= -9996
paInvalidFlag	= -9995
paSampleFormatNotSupported	= -9994
paBadIODeviceCombination	= -9993
paInsufficientMemory	= -9992
paBufferTooBig	= -9991
paBufferTooSmall	= -9990
paNullCallback	= -9989
paBadStreamPtr	= -9988
paTimedOut	= -9987
paInternalError	= -9986
paDeviceUnavailable	= -9985
paIncompatibleHostApiSpecificStreamInfo	= -9984
paStreamIsStopped	= -9983
paStreamIsNotStopped	= -9982
paInputOverflowed	= -9981
paOutputUnderflowed	= -9980
paHostApiNotFound	= -9979
paInvalidHostApi	= -9978
paCanNotReadFromACallbackStream	= -9977
paCanNotWriteToACallbackStream	= -9976
paCanNotReadFromAnOutputOnlyStream	= -9975
paCanNotWriteToAnInputOnlyStream	= -9974
paIncompatibleStreamHostApi	= -9973
paBadBufferPtr	= -9972

negative) if PortAudio is not initialized or an error is encountered.

### DefaultHostApiIndexd as integer

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the index of the default host API.

**Notes:**

The default host API will be the lowest common denominator host API on the current platform and is unlikely to provide the best performance.

Returns a non-negative value ranging from 0 to (HostApiCount-1) indicating the default host API index or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

**DefaultInputDeviceID as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the index of the default input device.

**Notes:**

The result can be used in the inputDevice parameter to OpenStream().

Returns the default input device index for the default host API, or paNoDevice (-1) if no default input device is available or an error was encountered.

**DefaultOutputDeviceID as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the index of the default output device.

**Notes:**

The result can be used in the outputDevice parameter to OpenStream().

Returns the default output device index for the default host API, or paNoDevice (-1) if no default output device is available or an error was encountered.

On the PC, the user can specify a default device by setting an environment variable. For example, to use device # 1.

```
set PA_RECOMMENDED_OUTPUT_DEVICE=1
```

The user should first determine the available device ids by using the supplied application "pa\_devs".

**DeviceInfo(DeviceIndex as integer) as PortAudioDeviceInfoMBS**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve an object containing information about the specified device.

**Notes:**

Returns an object of class PortAudioDeviceInfoMBS with the requested information. If the device parameter is out of range the function returns nil.

DeviceIndex: A valid device index in the range 0 to (PortAudioMBS.CountDevices-1)

**ErrorText(ErrorNumber as integer) as string**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Translate the error number into a human readable message.

**GetSampleSize(Format as integer) as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns the sample size in bytes of the given format.

**HostApiCount as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the number of available host APIs.

**Notes:**

Even if a host API is available it may have no devices available.

Returns a non-negative value indicating the number of available host APIs or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

**HostApiDeviceIndexToDeviceIndex(hostApiIndex as integer, hostApiDeviceIndex as integer) as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Convert a host-API-specific device index to standard PortAudio device index.

**Notes:**

This function may be used in conjunction with the deviceCount field of PaHostApiInfo to enumerate all devices for the specified host API.

hostApiIndex: A valid host API index ranging from 0 to (HostApiCount-1)

hostApiDeviceIndex: A valid per-host device index in the range 0 to (HostApiInfo(hostApi).deviceCount-1)

Returns a non-negative device index ranging from 0 to (DeviceCount-1) or, an error code (which are always negative) if PortAudio is not initialized or an error is encountered.

A paInvalidHostApi (-9978) error code indicates that the host API index specified by the hostApi parameter is out of range.

A paInvalidDevice (-9996) error code indicates that the hostApiDeviceIndex parameter is out of range.

**HostApiInfo(hostApiIndex as integer) as PortAudioHostApiInfoMBS**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve an PortAudioHostApiInfoMBS object containing information about a specific host Api.

**Notes:**

hostApiIndex: A valid host API index ranging from 0 to (HostApiCount-1)

Returns the information object. If the hostApi parameter is out of range or an error is encountered, the function returns nil.

### HostApiTypeIdToHostApiIndex(type as integer) as integer

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Convert a static host API unique identifier, into a runtime host API index.

**Example:**

```
dim IndexDirectSound as integer
dim p as new PortAudioMBS
const paDirectSound=1
IndexDirectSound=p.HostApiTypeIdToHostApiIndex(paDirectSound)
```

**Notes:**

type: A unique host API identifier. See PortAudioHostApiInfoMBS.Type for the list of constants.

Returns a valid PaHostApiIndex ranging from 0 to (HostApiCount-1) or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

The paHostApiNotFound (-9979) error code indicates that the host API specified by the type parameter is not available.

### HostError as PortAudioHostErrorInfoMBS

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Return information about the last host error encountered.

**Notes:**

This function is provided as a last resort, primarily to enhance debugging by providing clients with access to all available error information.

Returns an object constaining information about the host error. The values in this structure will only be valid if a PortAudio function has previously returned the `paUnanticipatedHostError`.

**IsFormatSupported(input as PortAudioStreamParametersMBS, output as PortAudioStreamParametersMBS, sampleRate as double) as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Determine whether it would be possible to open a stream with the specified parameters.

**Notes:**

**input:** An object that describes the input parameters used to open a stream. The `suggestedLatency` field is ignored. `inputParameters` must be nil for output-only streams.

**output:** An object that describes the output parameters used to open a stream. The `suggestedLatency` field is ignored. `outputParameters` must be nil for input-only streams.

**sampleRate:** The required `sampleRate`. For full-duplex streams it is the sample rate for both input and output

Returns 0 if the format is supported, and an error code indicating why the format is not supported otherwise. The constant `paFormatIsSupported` (0) is provided to compare with the return value for success.

**SampleSize(theFormat as integer) as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Return size in bytes of a single sample in a given sample format or `paSampleFormatNotSupported` (-9994).

**Notes:**

Returns 0 on any error.

Constants for sample format:

```

const paFloat32      = 1
const paInt32        = 2
const paInt24        = 4
const paInt16        = 8
const paInt8         = 16
const paUInt8        = 32
const paCustomFormat = 65536
const paNonInterleaved = negative sign

```

The standard formats paFloat32, paInt16, paInt32, paInt24, paInt8 and aUInt8 are usually implemented by all implementations.

The floating point representation (paFloat32) uses +1.0 and -1.0 as the maximum and minimum respectively.

paUInt8 is an unsigned 8 bit format where 128 is considered "ground"

The paNonInterleaved flag indicates that a multichannel buffer is passed as a set of non-interleaved pointers.

### **Sleep(msec as integer)**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Put the caller to sleep for at least 'msec' milliseconds.

#### **Notes:**

This function is provided only as a convenience for authors of portable code (such as the tests and examples in the PortAudio distribution.)

The function may sleep longer than requested so don't rely on this for accurate musical timing.

**Version as integer**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve the release number of the currently running PortAudio build.

**Notes:** e.g. 1900

**VersionText as String**

method from class PortAudioMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve a textual description of the current PortAudio build.

**Notes:** e.g. "PortAudio V19-devel 13 October 2002"

## 2.6 class PortAudioHostApiInfoMBS

**class PortAudioHostApiInfoMBS**

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class containing information about a particular host API.

### 2.6.1 Properties

**defaultInputDevice as Integer**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The default input device for this host API.

**Notes:**

The value will be a device index ranging from 0 to (PortAudioHostApiInfoMBS.deviceCount-1), or paNoDevice (-1) if no default input device is available.  
(Read only property)

### **defaultOutputDevice as Integer**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The default output device for this host API.

**Notes:**

The value will be a device index ranging from 0 to (PortAudioHostApiInfoMBS.deviceCount-1), or paNoDevice (-1) if no default output device is available.  
(Read only property)

### **deviceCount as Integer**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The number of devices belonging to this host API.

**Notes:**

This field may be used in conjunction with HostApiDeviceIndexToDeviceIndex() to enumerate all devices for this host API.  
(Read only property)

### **Index as Integer**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The index of this host API.

**Notes:** (Read only property)

**Name as String**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A textual description of the host API for display on user interfaces.

**Notes:** (Read only property)

**Type as Integer**

property from class PortAudioHostApiInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The well known unique identifier of this host API.

**Notes:**

Useful constants for the different types:

paInDevelopment	=0
paDirectSound	=1
paMME	=2
paASIO	=3
paSoundManager	=4
paCoreAudio	=5
paOSS	=7
paALSA	=8
paAL	=9
paBeOS	=10
paWDMKS	=11
paJACK	=12
paWASAPI	=13
paAudioScienceHPI	=14

(Read only property)

## 2.7 class PortAudioStreamBaseMBS

### class PortAudioStreamBaseMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The base class for the portaudio streams.

### 2.7.1 Methods

#### Abort as integer

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Terminates audio processing immediately without waiting for pending buffers to complete.

#### Close as integer

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Closes an audio stream.

**Notes:** If the audio stream is active it discards any pending buffers as if Abort() had been called.

#### CPUload as double

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve CPU usage information for the specified stream.

**Notes:**

The "CPU Load" is a fraction of total CPU time consumed by a callback stream's audio processing routines

including, but not limited to the client supplied stream callback. This function does not work with blocking read/write streams.

This function may be called from the stream callback function or the application.

Returns a floating point value, typically between 0.0 and 1.0, where 1.0 indicates that the stream event is consuming the maximum number of CPU cycles possible to maintain real-time operation. A value of 0.5 would imply that PortAudio and the stream event was consuming roughly 50% of the available CPU time. The return value may exceed 1.0. A value of 0.0 will always be returned for a blocking read/write stream, or if an error occurs.

### HostError as PortAudioHostErrorInfoMBS

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Return information about the last host error encountered.

**Notes:**

This function is provided as a last resort, primarily to enhance debugging by providing clients with access to all available error information.

Returns an object constaining information about the host error. The values in this structure will only be valid if a PortAudio function has previously returned the paUnanticipatedHostError.

### Info as PortAudioStreamInfoMBS

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Retrieve a PortAudioStreamInfoMBS object containing information about the specified stream.

**Notes:** If the stream parameter invalid, or an error is encountered, the function returns nil.

**IsStreamActive as integer**

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Determine whether the stream is active.

**Notes:**

A stream is active after a successful call to Start(), until it becomes inactive either as a result of a call to Stop() or Abort(), or as a result of a return value other than paContinue from the stream callback. In the latter case, the stream is considered inactive after the last buffer has finished playing.

Returns one (1) when the stream is active (ie playing or recording audio), zero (0) when not playing or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

**IsStreamStopped as integer**

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Determine whether the stream is stopped.

**Notes:**

A stream is considered to be stopped prior to a successful call to Start and after a successful call to Stop or Abort.

If a stream value returns a value other than paContinue (0) the stream is NOT considered to be stopped.

Returns one (1) when the stream is stopped, zero (0) when the stream is running or, a PaErrorCode (which are always negative) if PortAudio is not initialized or an error is encountered.

**Start as integer**

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Commences audio processing.

**Notes:**

Returns an error code.  
(0 for success, -1 for no stream)

### Stop as integer

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Terminates audio processing.

**Notes:** It waits until all pending audio buffers have been played before it returns.

### Time as double

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Determine the current time for the stream according to the same clock used to generate buffer timestamps.

**Notes:**

This time may be used for synchronising other events to the audio stream, for example synchronizing audio to MIDI.

Returns the stream's current time in seconds, or 0 if an error occurred.

### UseSafeThreading as boolean

method from class PortAudioStreamBaseMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Enables or disables thread safe event handling.

**Notes:**

Realbasic works normally only on one preemptive thread as the framework is not reentrant and not in general preemptive thread safe.

Still newer Realbasic versions get better so you can switch it off and get a better performance.

For most usages you need to turn it off. See the examples. A lot of pragma lines are needed to disable everything which can slow down processing. Also you are limited in a preemptive thread to do only math

and no object creating/deleting.  
(Read and Write computed property)

## 2.8 class PortAudioStreamRecorderMBS

### class PortAudioStreamRecorderMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A portaudio stream class to use an internal buffer to record audio.

**Notes:**

This class has a ring buffer to store the audio samples which they are being recorded. Your application can in a timer or thread process this samples.

Subclass of the PortAudioStreamBaseMBS class.

### 2.8.1 Methods

#### Constructor(BufferSize as integer)

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Creates a new object using a buffer of the given size.

**Notes:**

The buffer must be a power of 2. For example one Megabyte (2<sup>20</sup>).

At 44100 Hz, and 4 bytes per value and 2 channels, you will need 352800 bytes per second on storage.

**Flush**

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 10.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Clears the buffer and discards all current samples.

**OpenDefaultStream(numInputChannels as integer, sampleRate as double) as integer**

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A simplified version of OpenStream() that opens the default input devices.

**Notes:**

Sampleformat is always 32bit float in this class. (use memoryblock.singlevalue)

numInputChannels: The number of channels of sound to be delivered. It can range from 1 to the value of maxInputChannels in the PortAudioDeviceInfoMBS object for the default output device. If 0 the stream is opened as an output-only stream.

sampleRate: Same as OpenStream parameter of the same name.

Returns an error code.

Error -2 is from the plugin and reports that the buffer was not created before.

**OpenStream(inputParameters as PortAudioStreamParametersMBS, sampleRate as double, framesPerBuffer as integer, streamFlags as integer) as integer**

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Opens a stream for input.

**Notes:**

Sampleformat is always 32bit float in this class. (use memoryblock.singlevalue)

outputParameters: A object that describes the input parameters used by the opened stream. See PortAudioStreamParametersMBS for a description of these parameters.

sampleRate: The desired sampleRate.

framesPerBuffer: The number of frames passed to the stream callback function, or the preferred block granularity for a blocking read/write stream. The special value paFramesPerBufferUnspecified (0) may be used to request that the stream callback will receive an optimal (and possibly varying) number of frames based on host requirements and the requested latency settings.

Note: With some host APIs, the use of non-zero framesPerBuffer for a callback stream may introduce an additional layer of buffering which could introduce additional latency. PortAudio guarantees that the additional latency will be kept to the theoretical minimum however, it is strongly recommended that a non-zero framesPerBuffer value only be used when your algorithm requires a fixed number of frames per stream callback.

const paFramesPerBufferUnspecified=0

streamFlags: Flags which modify the behaviour of the streaming process. This parameter may contain a combination of flags ORed together. Some flags may only be relevant to certain buffer formats.

const paNoFlag	= 0	no flags
const paClipOff	= 1	Disable default clipping of out of range samples.
const paDitherOff	= 2	Flag requests that where possible a full duplex stream will not discard overflowed input samples without calling the stream callback. This flag is only valid for full duplex callback streams and only when used in combination with the paFramesPerBufferUnspecified (0) framesPerBuffer parameter. Using this flag incorrectly results in a paInvalidFlag error being returned from OpenStream and OpenDefaultStream.
const paNeverDropInput	= 4	Call the stream callback to fill initial output buffers, rather than the default behavior of priming the buffers with zeros (silence). This flag has no effect for input-only and blocking read/write streams.
const paPrimeOutputBuffersUsingStreamCallback	= 8	Call the stream callback to fill initial output buffers, rather than the default behavior of priming the buffers with zeros (silence). This flag has no effect for input-only and blocking read/write streams.

Upon success OpenStream() returns paNoError and places a pointer to a valid PaStream in the stream argument. The stream is inactive (stopped).

If a call to OpenStream() fails, a non-zero error code is returned (see PaError for possible error codes) and the value of stream is invalid.

Error -2 is from the plugin and reports that the buffer was not created before.

**ReadFrames(mem as memoryblock, SizeInBytes as integer) as integer**

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Reads frames into the memoryblock.

**Example:**

```
dim s as PortAudioStreamRecorderMBS
dim m as memoryblock

m=newmemoryblock(1024*1024)
// initialize

dim frames as integer

frames=s.ReadFrames(m,m.size)

msgbox "we got "+str(frames)+" frames."
```

**Notes:**

You pass a memoryblock and the size of this memoryblock in bytes.

Values are stored in floats (memoryblock.singlevalue) so you get at maximum SizeInBytes/4 values. And if you use more than one channel, you will receive them interlaced.

ReadFrames uses a mutex to access share data, so this call is expensive. Use a big buffer.

**ResizeBuffer(BufferSize as integer)**

method from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Resizes the buffer.

**Notes:**

Do not resize while you are recording (this can crash).

The buffer must be a power of 2. For example one Megabyte (2<sup>20</sup>).

At 44100 Hz, and 4 bytes per value and 2 channels, you will need 352800 bytes per second on storage.

## 2.8.2 Properties

### Buffer as Memoryblock

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 10.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns a memoryblock which points to the ring buffer used in the recorder object.

**Notes:**

This memoryblock has no size.

It is only for debugging and only valid as long as the PortAudioStreamRecorderMBS object is living.

(Read only property)

### BufferReadIndex as Integer

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 10.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The read index inside the ring buffer.

**Notes:**

Only for debugging.

(Read only property)

### BufferSize as Integer

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 10.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The size of the ring buffer in bytes.

**Notes:** (Read only property)

**BufferWriteIndex as Integer**

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 10.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The write index inside the ring buffer.

**Notes:**

Only for debugging.  
(Read only property)

**FramesAvailable as Integer**

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The number of frames available in the buffer.

**Notes:**

FramesAvailable uses a mutex to access share data, so this call is expensive. Do not call it to decide whether to call ReadFrames. ReadFrames calls FramesAvailable itself.  
(Read only property)

**NumInputChannels as Integer**

property from class PortAudioStreamRecorderMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The number of input channels used with the OpenStream function.

**Notes:** (Read only property)

## 2.9 class PortAudioStreamParametersMBS

### class PortAudioStreamParametersMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Parameters for one direction (input or output) of a stream.

### 2.9.1 Properties

#### ChannelCount as Integer

property from class PortAudioStreamParametersMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The requested channel count.

**Notes:**

The number of channels of sound to be delivered to the stream callback or accessed by Read() or Write(). It can range from 1 to the value of maxInputChannels in the DeviceInfo object for the device specified by the device parameter.

(Read and Write property)

#### Device as Integer

property from class PortAudioStreamParametersMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The device ID to be used.

**Notes:**

A valid device index in the range 0 to (PortAudioMBS.CountDevices-1) specifying the device to be used or the special constant paUseHostApiSpecificDeviceSpecification which indicates that the actual device(s) to use are specified in hostApiSpecificStreamInfo.

This field must not be set to paNoDevice (-1).

(Read and Write property)

**SampleFormat as Integer**

property from class PortAudioStreamParametersMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The sample format of the buffer provided to the stream callback, Read() or Write().

**Notes:**

Constants for sample format:

```

const paFloat32      = 1
const paInt32        = 2
const paInt24        = 4
const paInt16        = 8
const paInt8         = 16
const paUInt8        = 32
const paCustomFormat = 65536
const paNonInterleaved = negative sign

```

The standard formats paFloat32, paInt16, paInt32, paInt24, paInt8 and aUInt8 are usually implemented by all implementations.

The floating point representation (paFloat32) uses +1.0 and -1.0 as the maximum and minimum respectively.

paUInt8 is an unsigned 8 bit format where 128 is considered "ground"

The paNonInterleaved flag indicates that a multichannel buffer is passed as a set of non-interleaved pointers. (Read and Write property)

**SuggestedLatency as Double**

property from class PortAudioStreamParametersMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The desired latency in seconds.

**Notes:**

Where practical, implementations should configure their latency based on these parameters, otherwise they may choose the closest viable latency instead. Unless the suggested latency is greater than the absolute

upper limit for the device implementations should round the suggestedLatency up to the next practical value - ie to provide an equal or higher latency than suggestedLatency wherever possible.  
Actual latency values for an open stream may be retrieved using the inputLatency and outputLatency fields of the PortAudioStreamInfoMBS object returned by PortAudioStreamMBS.Info().  
(Read and Write property)

## 2.10 class PortAudioDeviceInfoMBS

### class PortAudioDeviceInfoMBS

class, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class providing information and capabilities of PortAudio devices.

**Notes:** Devices may support input, output or both input and output.

### 2.10.1 Properties

#### DefaultHighInputLatency as Double

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Default latency values for robust non-interactive applications (eg. playing sound files).

**Notes:** (Read only property)

#### DefaultHighOutputLatency as Double

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Default latency values for robust non-interactive applications (eg. playing sound files).

**Notes:** (Read only property)

**DefaultLowInputLatency as Double**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Default latency values for interactive performance.

**Notes:** (Read only property)

**DefaultLowOutputLatency as Double**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Default latency values for interactive performance.

**Notes:** (Read only property)

**DefaultSampleRate as Double**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The default sample rate.

**Notes:** (Read only property)

**HostApiIndex as Integer**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The host API index for this device.

**Notes:** (Read only property)

**Index as Integer**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 7.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The index of this device.

**Notes:** (Read only property)

**MaxInputChannels as integer**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The number of input channels.

**Notes:**

Returns 0 on any error.

(Read only property)

**MaxOutputChannels as integer**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The number of output channels for this device.

**Notes:**

0 on any error.

Seems like an iMac returns two here, but the internal microphone has only one channel. So be aware that the memoryblocks in the events do have the actual size of the data that is coming in. So stereo has there a larger buffer.

(Read only property)

**Name as String**

property from class PortAudioDeviceInfoMBS, Audio, MBS REALbasic Audio Plugin (PortAudio), Plugin  
version: 6.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The name of this device.

**Notes:**

Returns "" on any error.

(Read only property)

# Chapter 3

## MIDI

### 3.1 class PortMidiStreamMBS

**class PortMidiStreamMBS**

class, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The Realbasic class to represent a PortMidi stream.

**Notes:** A single PortMidiStream is a descriptor for an open MIDI device.

#### 3.1.1 Methods

**Abort as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Terminates outgoing messages immediately.

**Notes:**

The caller should immediately close the output port; this call may result in transmission of a partial midi message. There is no abort for Midi input because the user can simply ignore messages in the buffer and close an input device at any time.

Returns an error code.

### Close

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The destructor.

**Notes:**

There is no need to call this method except you want to free all resources of this object now without waiting for Realbasic to do it for you.

(e.g. some Realbasic versions crash on Windows if there are plugin objects not closed.)

### ErrorText(ErrorNumber as integer) as string

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The error message for this error number.

### OpenInput(DeviceID as integer, BufferSize as integer) as integer

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Opens a device for reading.

**Notes:**

DeviceID is the id of the device used for input.

For input, the buffersize specifies the number of input events to be buffered waiting to be read using Pm\_Read().

(In some cases – see below – PortMidi does not buffer output at all and merely passes data to a lower-level API, in which case buffersize is ignored.)

Latency is the delay in milliseconds applied to timestamps to determine when the output should actually occur. (If latency is <0, 0 is assumed.)

If latency is zero, timestamps are ignored and all output is delivered immediately. If latency is greater than zero, output is delayed until the message timestamp plus the latency. (NOTE: time is measured relative to the time source indicated by time\_proc. Timestamps are absolute, not relative delays or offsets.) In some cases, PortMidi can obtain better timing than your application by passing timestamps along to the device driver or hardware. Latency may also help you to synchronize midi data to audio data by matching midi latency to the audio buffer latency.

return value:

Upon success OpenInput returns PmNoError.

If a call to OpenInput fails a nonzero error code is returned (see PmError above) and the value of port is invalid.

### **OpenOutput(DeviceID as integer, BufferSize as integer, Latency as integer) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Opens a device for writing.

**Notes:**

DeviceID is the id of the device used for input.

For output, buffersize specifies the number of output events to be buffered waiting for output.

(In some cases – see below – PortMidi does not buffer output at all and merely passes data to a lower-level API, in which case buffersize is ignored.)

return value:

Upon success OpenInput returns PmNoError.

If a call to OpenInput fails a nonzero error code is returned (see PmError above) and the value of port is invalid.

### **Poll as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Tests whether input is available,  
**Notes:** Returns 1 on success and 0 on failure.

### **Read(byref data as PortMidiEventMBS) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Reads midi data.  
**Notes:**

Returns the number of read items.  
 (0 for error and 1 for success)

Read retrieves midi data into a buffer, and returns the number of events read. Result is a non-negative number unless an error occurs, in which case a PmError value will be returned.

### Buffer Overflow

The problem: if an input overflow occurs, data will be lost, ultimately because there is no flow control all the way back to the data source. When data is lost, the receiver should be notified and some sort of graceful recovery should take place, e.g. you shouldn't resume receiving in the middle of a long sysex message.

With a lock-free fifo, which is pretty much what we're stuck with to enable portability to the Mac, it's tricky for the producer and consumer to synchronously reset the buffer and resume normal operation.

Solution: the buffer managed by PortMidi will be flushed when an overflow occurs. The consumer (Read()) gets an error message (pmBufferOverflow) and ordinary processing resumes as soon as a new message arrives. The remainder of a partial sysex message is not considered to be a "new message" and will be flushed as well.

### **SetChannelMask(mask as integer) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Filters incoming messages based on channel.

**Example:**

```
dim s as PortMidiStreamMBS // your midi stream
```

```
call s.SetChannelMask(1+4) // Channel 1 and 3.
```

**Notes:**

The mask is a 16-bit bitfield corresponding to appropriate channels

All channels are allowed by default.

Returns an error code.

**SetFilter(filters as integer) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** SetFilter() sets filters on an open input stream to drop selected input types.

**Notes:**

By default, only active sensing messages are filtered.

To prohibit, say, active sensing and sysex messages, call SetFilter(FilterActive + FilterSysEx);

Filtering is useful when midi routing or midi thru functionality is being provided by the user application.

For example, you may want to exclude timing messages (clock, MTC, start/stop/continue), while allowing note-related messages to pass.

Or you may be using a sequencer or drum-machine for MIDI clock information but want to exclude any notes it may play.

Returns an error code.

**Write(data as PortMidiEventMBS) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Writes midi data from a buffer.

**Notes:**

This may contain:

- short messages or
- sysex messages that are converted into a sequence of PortMidiStreamMBS objects, e.g. sending data from a file or forwarding them from midi input.

Use WriteSysEx() to write a sysex message stored as a contiguous array of bytes.

Sysex data may contain embedded real-time messages.

Returns an error code.

### **WriteShort(When as integer, message as integer) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Writes a timestamped non-system-exclusive midi message.

**Notes:** Messages are delivered in order as received, and timestamps must be non-decreasing. (But timestamps are ignored if the stream was opened with latency = 0.)

### **WriteSysEx(When as integer, message as memoryblock, offset as integer) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.1, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Writes a timestamped system-exclusive midi message.

**Notes:**

The data is taken from the memoryblock at the given offset.

The message must be 0 terminated.

This message must be valid and contain the special start value and a EOX value on the end.

See also:

- 3.1.1 WriteSysEx(When as integer, message as string) as integer

**WriteSysEx(When as integer, message as string) as integer**

method from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Writes a timestamped system-exclusive midi message.

**Notes:** This message must be valid and contain the special start value and a EOX value on the end.

See also:

- 3.1.1 WriteSysEx(When as integer, message as memoryblock, offset as integer) as integer 64

### 3.1.2 Properties

**ChannelMask as Integer**

property from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The channel mask used.

**Notes:**

Use SetChannelMask to change it.

(Read only property)

**Filters as Integer**

property from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The filters setting.

**Notes:**

Use SetFilters to change it.

(Read only property)

### 3.1.3 Constants

#### **FilterActive = & h4000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter active sensing messages (& hFE)

#### **FilterAftertouch = & h6000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter both channel and poly aftertouch

#### **FilterChannelAftertouch = & h20000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter channel aftertouch (most midi controllers use this) (& hD0-& hDF)

#### **FilterClock & h1D00**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter clock messages (CLOCK & hF8, START & hFA, STOP & hFC, and CONTINUE & hFB)

**FilterControl & h8000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Control Changes (CC's) (& hB0-& hBF)

**FilterFD = & h2000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter undefined FD messages

**FilterMTC = 2**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** MIDI Time Code (& hF1)

**FilterNote = & h3000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter note-on and note-off (& h90-& h9F and & h80-& h8F)

**FilterPitchBend = & h40000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Pitch Bender (& hE0-& hEF)

**FilterPlay = & h400**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter play messages (start & hFA, stop & hFC, continue & hFB)

**FilterPolyAftertouch = & h4000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** per-note aftertouch (& hA0-& hAF)

**FilterProgram = & h10000000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Program changes (& hC0-& hCF)

**FilterRealTime = & hFF01**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter all real-time messages

**FilterReset = & h8000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter reset messages (& hFF)

**FilterSongPosition = 4**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Song Position (& hF2)

**FilterSongSelect = 8**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Song Select (& hF3)

**FilterSysEx = 1**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter system exclusive messages (& hF0)

**FilterSystemCommon = & h4E**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** All System Common messages (mtc, song position, song select, tune request)

**FilterTick = & h200**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter tick messages (& hF9)

**FilterTune = & h40**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** Tuning request (& hF6)

**FilterUndefined = & h2000**

const from class PortMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi filter constants.

**Notes:** filter undefined real-time messages

## 3.2 class PortMidiDeviceInfoMBS

**class PortMidiDeviceInfoMBS**

class, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** A class for device information.

### 3.2.1 Properties

**HasInput as Boolean**

property from class PortMidiDeviceInfoMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** True if input is available.

**Notes:** (Read only property)

**HasOutput as Boolean**

property from class PortMidiDeviceInfoMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** True if output is available.

**Notes:** (Read only property)

### InterfaceName as String

property from class PortMidiDeviceInfoMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Underlying MIDI API.

**Notes:**

e.g. MMSystem, DirectX or CoreMidi.  
(Read only property)

### Name as String

property from class PortMidiDeviceInfoMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The device name.

**Notes:**

e.g. USB MidiSport 1x1  
(Read only property)

## 3.3 class PortMidiMBS

### class PortMidiMBS

class, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The PortMidi library wrapped for use in Realbasic.

**Notes:**

Error codes:

```

const pmNoError          = 0
const pmHostError       = -10000
const pmInvalidDeviceId = -9999
const pmInsufficientMemory = -9998
const pmBufferTooSmall  = -9997
const pmBufferOverflow  = -9996
const pmBadPtr          = -9995
const pmBadData         = -9994
const pmInternalError   = -9993
const pmBufferMaxSize   = -9992

```

### 3.3.1 Methods

#### CountDevices as integer

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Counts the devices.

**Notes:** Returns 0 on any error.

#### DefaultInputDeviceID as integer

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns the default device ID or pmNoDevice (-1) if there are no devices.

**Notes:**

On the PC, the user can specify a default device by setting an environment variable. For example, to use device # 1.

```
set PM_RECOMMENDED_OUTPUT_DEVICE=1
```

The user should first determine the available device ID by using the supplied application "testin" or "testout".

In general, the registry is a better place for this kind of info, and with USB devices that can come and go, using integers is not very reliable for device identification. Under Windows, if PM\_RECOMMENDED\_OUTPUT\_DEVICE (or PM\_RECOMMENDED\_INPUT\_DEVICE) is *\*NOT\** found in the

environment, then the default device is obtained by looking for a string in the registry under: HKEY\_LOCAL\_MACHINE/SOFTWARE/PortMidi/Recommended\_Input\_Device and HKEY\_LOCAL\_MACHINE/SOFTWARE/PortMidi/Recommended\_Output\_Device for a string. The number of the first device with a substring that matches the string exactly is returned. For example, if the string in the registry is "USB", and device 1 is named "In USB MidiSport 1x1", then that will be the default input because it contains the string "USB".

In addition to the name, PmDeviceInfo has the member "interf", which is the interface name. (The "interface" is the underlying software system or API used by PortMidi to access devices. Examples are MMSystem, DirectX (not implemented), ALSA, OSS (not implemented), etc.) At present, the only Win32 interface is "MMSystem", the only Linux interface is "ALSA", and the only Mac OS X interface is "CoreMIDI".

To specify both the interface and the device name in the registry, separate the two with a comma and a space, e.g.:

MMSystem, In USB MidiSport 1x1

In this case, the string before the comma must be a substring of the "interf" string, and the string after the space must be a substring of the "name" name string in order to match the device.

Note: in the current release, the default is simply the first device (the input or output device with the lowest PmDeviceID).

### DefaultOutputDeviceID as integer

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns the default device ID or pmNoDevice (-1) if there are no devices.

**Notes:**

On the PC, the user can specify a default device by setting an environment variable. For example, to use device # 1.

```
set PM_RECOMMENDED_OUTPUT_DEVICE=1
```

The user should first determine the available device ID by using the supplied application "testin" or "testout".

In general, the registry is a better place for this kind of info, and with USB devices that can come and go, using integers is not very reliable for device identification. Under Windows, if PM\_RECOMMENDED\_OUTPUT\_DEVICE (or PM\_RECOMMENDED\_INPUT\_DEVICE) is \*NOT\* found in the environment, then the default device is obtained by looking for a string in the registry under: HKEY\_LOCAL\_MACHINE/SOFTWARE/PortMidi/Recommended\_Input\_Device and HKEY\_LOCAL\_MACHINE/SOFTWARE/PortMidi/Recommended\_Output\_Device for a string. The number of the first device

with a substring that matches the string exactly is returned. For example, if the string in the registry is "USB", and device 1 is named "In USB MidiSport 1x1", then that will be the default input because it contains the string "USB".

In addition to the name, PmDeviceInfo has the member "interf", which is the interface name. (The "interface" is the underlying software system or API used by PortMidi to access devices. Examples are MMSYSTEM, DirectX (not implemented), ALSA, OSS (not implemented), etc.) At present, the only Win32 interface is "MMSYSTEM", the only Linux interface is "ALSA", and the only Mac OS X interface is "CoreMIDI".

To specify both the interface and the device name in the registry, separate the two with a comma and a space, e.g.:

MMSYSTEM, In USB MidiSport 1x1

In this case, the string before the comma must be a substring of the "interf" string, and the string after the space must be a substring of the "name" name string in order to match the device.

Note: in the current release, the default is simply the first device (the input or output device with the lowest PmDeviceID).

### DeviceInfo(DeviceID as integer) as PortMidiDeviceInfoMBS

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Returns information about a certain device.

**Notes:** Returns nil on any error.

### ErrorText(ErrorNumber as integer) as string

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The error text for the given error code.

**Notes:** Returns "" on any error.

### ReInitialize as integer

method from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Shuts down PortMidi and initializes it again.

**Notes:**

As PortMidi does not recognize the attachment of new MIDI devices, you can only reinitialize.

Returns a PortMidi error code.

### 3.3.2 Constants

**pmBadData = -9994**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**Notes:** illegal midi data, e.g. missing EOX

**pmBadPtr = -9995**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmBufferSize = -9992**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**Notes:** buffer is already as large as it can be.

**pmBufferOverflow = -9996**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmBufferTooSmall = -9997**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmHostError = -10000**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmInsufficientMemory = -9998**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmInternalError = -9993**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmInvalidDeviceId = -9999**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**Notes:** out of range or output device when input is requested or input device when output is requested or device is already opened.

**pmNoDevice = -1**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

**pmNoError = 0**

const from class PortMidiMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 9.4, not console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** One of the PortMidi errors.

### 3.4 class PortMidiEventMBS

**class PortMidiEventMBS**

class, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The class for a piece of midi data.

### 3.4.1 Methods

**Set(status as integer, data1 as integer, data2 as integer)**

method from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Sets the value to the given data.

**SetRaw(data0 as integer, data1 as integer, data2 as integer, data3 as integer)**

method from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 11.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** Sets the raw data by setting all 4 bytes together.

### 3.4.2 Properties

**Data1 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The first data value in the midi event.

**Notes:** (Read and Write property)

**Data2 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The second data value in the midi event.

**Notes:** (Read and Write property)

### **RawData0 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 11.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The first byte of the raw data in this event.

**Notes:**

Same as Status property.  
(Read and Write property)

### **RawData1 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 11.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The second byte of the raw data in this event.

**Notes:**

Same as Data1 property.  
(Read and Write property)

### **RawData2 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 11.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The third byte of the raw data in this event.

**Notes:**

Same as Data2 property.  
(Read and Write property)

**RawData3 as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 11.0, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The forth byte of the raw data in this event.

**Notes:** (Read and Write property)

**RawMessage as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.4, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The raw content of the event as a integer.

**Notes:**

Take care about platform differences like the byte order.  
(Read and Write property)

**Status as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The status value.

**Notes:** (Read and Write property)

**When as Integer**

property from class PortMidiEventMBS, MIDI, MBS REALbasic Audio Plugin (PortMidi), Plugin version: 5.2, console safe, Mac OS X: Works, Windows: Works, Linux x86: Works.

**Function:** The time value of this midi data.

**Notes:**

Should be milliseconds.  
(Read and Write property)

## 3.5 class WindowsMidiOutputMBS

### class WindowsMidiOutputMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A class to represent a Midi Output device.

**Notes:** Subclass of the WindowsMidiMBS class.

### 3.5.1 Methods

#### Close

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Closes the output device.

**Notes:**

Closes the device with waiting till device is done.

Handle is set to 0 and lasterror is set.

#### Open(DeviceID as integer)

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Opens the midi device with the given index.

**Notes:**

DeviceID is from 0 to NumberOfMidiOutputDevices-1.

Lasterror is set.

### OpenDefault

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Opens the Midi mapper which opens the device the user selected as the default midi device.

**Notes:**

If only one midi output device is available this one is opened.

On success the handle property is not zero.

Lasterror is set.

### OutputErrorText(errorcode as integer) as string

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Translates an error number into a human readable text.

**Notes:**

Returns "" on unknown errors.

String returned has Windows ANSI text encoding.

### Reset

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Resets the output device.

**Notes:** Lasterror is set.

### SendData(data as memoryblock, size as integer)

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends sysex data.

**Example:**

```

dim m as MemoryBlock
dim o as WindowsMidiOutputMBS // your midi output

m=NewMemoryBlock(8)

m.Byte(0)=& hF0
m.Byte(1)=& h7F
m.Byte(2)=& h7F
m.Byte(3)=& h04
m.Byte(4)=& h01
m.Byte(5)=& h7F
m.Byte(6)=& h7F
m.Byte(7)=& hF7

o.SendData m

```

**Notes:**

Lasterror is set.  
size is the size of the memoryblock to use. A wrong value will crash the application.  
See also:

- 3.5.1 SendData(data as string)

84

**SendData(data as string)**

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin  
version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends sysex data.

**Notes:** Lasterror is set.

See also:

- 3.5.1 SendData(data as memoryblock, size as integer)

83

**SendMessage(message as integer)**

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends a short midi message immediately.

**Example:**

```
dim o as WindowsMidiOutputMBS // your windows midi output
// & h90 = Note down
// & h43 = the note number
// & h40 = the velocity
o.SendMessage & h404390
```

**Notes:**

The message is stored in one 32bit integer.

lowest 8 bit is status, second 8 bit is data1, third 8 bit is data2 and highest 8 bit is left 0.

Between sending note on and off messages, you need to leave time for actual playback.

Lasterror is set.

See also:

- 3.5.1 SendMessage(status as integer, data1 as integer, data2 as integer)

**SendMessage(status as integer, data1 as integer, data2 as integer)**

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends a short midi message immediately.

**Example:**

```
dim o as WindowsMidiOutputMBS // your windows midi output
// & h90 = Note down
// & h3C = the note number
// & h40 = the velocity
o.SendMessage & h90, & h3C, & h40
```

**Notes:**

Lasterror is set.

Between sending note on and off messages, you need to leave time for actual playback.

See also:

- 3.5.1 SendMessage(message as integer)

85

**Volume as integer**

method from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The volume to be used for this device.

**Example:**

```
dim m as WindowsMidiOutputMBS // your midi output

m.Volume=0 // all silent
m.Volume=& hFFFF0000 // right only
m.Volume=& h0000FFFF // left only or max volume for mono device
m.Volume=& h7FFF7FFF // half volume for both channels
```

**Notes:**

Not all devices can set the volume.

Lasterror is set.

The low-order word contains the left-channel volume setting, and the high-order word contains the right-channel setting. A value of & hFFFF represents full volume, and a value of & h0000 is silence.

If a device does not support both left and right volume control, the low-order word of dwVolume specifies the mono volume level, and the high-order word is ignored.

(Read and Write computed property)

### 3.5.2 Events

#### DeviceClose

event from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** An event called when the device is closed.

**Notes:** Should be called when you call close or the object dies.

#### DeviceDataSent

event from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** An event called whenever SysEx data was sent.

#### DeviceOpen

event from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** An event called whenever the device was opened successfully.

#### DevicePositionCallback

event from class WindowsMidiOutputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Called when a MEVT\_F\_CALLBACK Midi event is about to be executed.

**Notes:** A way to track progress in playback.

## 3.6 class WindowsMidiStreamMBS

### class WindowsMidiStreamMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A class for a Windows Midi Stream.

### 3.6.1 Methods

#### Close

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Closes the Midi stream.

#### Open(DeviceID as integer)

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Opens a MIDI stream for output.

**Notes:**

By default, the device is opened in paused mode.

Lasterror is set.

DeviceID: The device is opened on behalf of the stream and closed again when the stream is closed.

#### Pause

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Pauses playback of a specified MIDI stream.

**Notes:** Lasterror is set.

#### **PositionBytes as integer**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Position of the stream in bytes.

**Notes:** Lasterror is set.

#### **PositionMS as integer**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:**

Position of the stream in milliseconds.

**Notes:** Lasterror is set.

#### **PositionSamples as integer**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Position of the stream in samples.

**Notes:** Lasterror is set.

#### **PositionTicks as integer**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Position of the stream in ticks.

**Notes:** Lasterror is set.

### Restart

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The Restart function restarts a paused MIDI stream.

**Notes:** Lasterror is set.

### SendMessage(message as integer)

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends a short midi message immediately.

**Example:**

```
dim o as WindowsMidiStreamMBS // your midi stream

// & h90 = Note down
// & h43 = the note number
// & h40 = the velocity
o.SendMessage & h404390
```

### Notes:

The message is stored in one 32bit integer.

lowest 8 bit is status, second 8 bit is data1, third 8 bit is data2 and highest 8 bit is left 0.

Between sending note on and off messages, you need to leave time for actual playback.

Lasterror is set.

See also:

- 3.6.1 SendMessage(status as integer, data1 as integer, data2 as integer)

**SendMessage(status as integer, data1 as integer, data2 as integer)**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Sends a short midi message immediately.

**Example:**

```
dim o as WindowsMidiStreamMBS // your midi stream

// & h90 = Note down
// & h3C = the note number
// & h40 = the velocity
o.SendMessage & h90, & h3C, & h40
```

**Notes:**

Lasterror is set.

Between sending note on and off messages, you need to leave time for actual playback.

See also:

- 3.6.1 SendMessage(message as integer)

90

**Stop**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The Stop function turns off all notes on all MIDI channels for the specified MIDI output device.

**Notes:** Lasterror is set.

**Tempo as integer**

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Tempo of the stream, in microseconds per quarter note.

**Notes:**

The tempo is honored only if the time division for the stream is specified in quarter note format.  
 Lasterror is set.  
 (Read and Write computed property)

### TimeDiv as integer

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Time division for this stream, in the format specified in the Standard MIDI Files 1.0 specification.  
**Notes:**

The low 16 bits of this integer value contain the time division.  
 Lasterror is set.  
 (Read and Write computed property)

### Volume as integer

method from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The volume to be used for this stream.  
**Example:**

```
dim m as WindowsMidiStreamMBS // your midi stream

m.Volume=0 // all silent
m.Volume=& hFFFF0000 // right only
m.Volume=& h0000FFFF // left only or max volume for mono device
m.Volume=& h7FFF7FFF // half volume for both channels
```

### Notes:

Not all devices can set the volume.  
 Lasterror is set.

The low-order word contains the left-channel volume setting, and the high-order word contains the right-

channel setting. A value of & hFFFF represents full volume, and a value of & h0000 is silence.

If a device does not support both left and right volume control, the low-order word of dwVolume specifies the mono volume level, and the high-order word is ignored.

Lasterror is set.

(Read and Write computed property)

### 3.6.2 Properties

#### Handle as Integer

property from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The handle for the midi stream.

**Notes:**

Type is HMIDISTRM.

(Read only property)

#### Lasterror as Integer

property from class WindowsMidiStreamMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The last error code reported by one of the class functions.

**Notes:** (Read only property)

## 3.7 class WindowsMidiInputMBS

### class WindowsMidiInputMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A class to represent an open Midi Input device in Realbasic.

**Notes:** Subclass of the WindowsMidiMBS class.

### 3.7.1 Methods

#### Close

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Closes the device.

**Notes:**

First stops recording, second resets midi output device and third Closes the device with waiting till device is done.

Handle is set to 0 and lasterror is set.

#### Idle

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 9.7, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Processes events.

**Notes:**

Midi events are buffered in data structures. This method dispatches them to the Realbasic event handlers. Call this method as often as you need events to fire. For example every 100ms in a timer.

same as WindowsMidiMBS.Idle

#### InputErrorText(errorcode as integer) as string

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Translates an error number into a human readable text.

**Notes:**

Returns "" on unknown errors.  
String returned has Windows ANSI text encoding.

**Open(DeviceID as integer, BufferSize as integer)**

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin  
version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Opens a Midi device.

**Notes:**

DeviceID is from 0 to NumberOfMidiInputDevices-1.  
Buffersize is the maximum size to allocate for each SysEx receive buffer.  
Minimum is 256 bytes. Windows does not handle SysEx messages bigger than 64K.  
Lasterror is set.  
On success the handle property is non zero.

**Reset**

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin  
version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Resets the device.

**Notes:** Lasterror is set.

**Start**

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin  
version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Starts listening for events.

**Notes:** Lasterror is set.

## Stop

method from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Stops recording.

**Notes:**

Lasterror is set.

You should not need this and just call close or let the object die.

## 3.7.2 Events

### DeviceClose

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** An event called whenever the output device is closed.

**Notes:** Called when you call close.

### DeviceData(timestamp as integer, status as integer, data1 as integer, data2 as integer)

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A simple Midi message has been received.

**Notes:**

Process this event fast to avoid losing events.

Status, Data1 and Data2 are all 8 bit values.

The time stamp is specified in milliseconds, beginning at zero when the Start function was called.

**DeviceError(timestamp as integer, status as integer, data1 as integer, data2 as integer)**

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A bad Midi message has been received.

**Notes:**

Process this event fast to avoid losing events.

Status, Data1 and Data2 are all 8 bit values.

The time stamp is specified in milliseconds, beginning at zero when the Start function was called.

**DeviceLongData(timestamp as integer, data as string)**

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** SysEx data was received.

**Notes:**

If data is "" no free buffer was available to store the data.

The time stamp is specified in milliseconds, beginning at zero when the Start function was called.

**DeviceLongError(timestamp as integer, data as string)**

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Bad SysEx data was received.

**Notes:**

If data is "" no free buffer was available to store the data.

The time stamp is specified in milliseconds, beginning at zero when the Start function was called.

## DeviceOpen

event from class WindowsMidiInputMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, not console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** An event called whenever the output device is opened.

**Notes:** Called when you call open.

## 3.8 class WindowsMidiInputInfoMBS

### class WindowsMidiInputInfoMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A class for information about a certain Midi Device.

### 3.8.1 Properties

#### DriverVersion as Integer

property from class WindowsMidiInputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Version number of the device driver for the MIDI input device.

**Notes:**

The high-order byte is the major version number, and the low-order byte is the minor version number.  
(Read only property)

#### Flags as Integer

property from class WindowsMidiInputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Some flags.

**Notes:**

Currently unused in Windows XP.  
(Read only property)

### ManufacturerID as Integer

property from class WindowsMidiInputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Manufacturer identifier of the device driver for the MIDI input device.

**Notes:** (Read only property)

### Name as String

property from class WindowsMidiInputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Product name.

**Notes:**

Currently an ANSI string.  
(Read only property)

### ProductID as Integer

property from class WindowsMidiInputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Product identifier of the MIDI input device.

**Notes:** (Read only property)

## 3.9 class WindowsMidiOutputInfoMBS

### class WindowsMidiOutputInfoMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** A class for information about a certain Midi Device.

### 3.9.1 Properties

#### ChannelMask as Integer

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Channels that an internal synthesizer device responds to, where the least significant bit refers to channel 0 and the most significant bit to channel 15.

**Notes:**

Port devices that transmit on all channels set this member to & hFFFF.  
(Read only property)

#### DriverVersion as Integer

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Version number of the device driver for the MIDI input device.

**Notes:**

The high-order byte is the major version number, and the low-order byte is the minor version number.  
(Read only property)

**Flags as Integer**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Optional functionality supported by the device.

**Notes:**

It can be one or more of the following:

MIDICAPS_ CACHE	= 4	Supports patch caching.
MIDICAPS_ LRVOLUME	= 2	Supports separate left and right volume control.
MIDICAPS_ STREAM	= 8	Provides direct support for the midiStreamOut function.
MIDICAPS_ VOLUME	= 1	Supports volume control.

If a device supports volume changes, the MIDICAPS\_ VOLUME flag will be set for the dwSupport member. If a device supports separate volume changes on the left and right channels, both the MIDICAPS\_ VOLUME and the MIDICAPS\_ LRVOLUME flags will be set for this member.  
(Read only property)

**ManufacturerID as Integer**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Manufacturer identifier of the device driver for the MIDI input device.

**Notes:** (Read only property)

**Name as String**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Product name.

**Notes:**

Currently an ANSI string.  
(Read only property)

**Notes as Integer**

property from class `WindowsMidiOutputInfoMBS`, `MIDI`, `MBS REALbasic Audio Plugin (WindowsMidi)`, Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Maximum number of simultaneous notes that can be played by an internal synthesizer device.

**Notes:**

If the device is a port, this member is not meaningful and is set to 0.

(Read only property)

**ProductID as Integer**

property from class `WindowsMidiOutputInfoMBS`, `MIDI`, `MBS REALbasic Audio Plugin (WindowsMidi)`, Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Product identifier of the MIDI input device.

**Notes:** (Read only property)

**Technology as Integer**

property from class `WindowsMidiOutputInfoMBS`, `MIDI`, `MBS REALbasic Audio Plugin (WindowsMidi)`, Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Type of the MIDI output device.

**Notes:**

This value can be one of the following:

```

MOD_ MIDIPORT      = 1 // output port
MOD_ SYNTH         = 2 // generic internal synth
MOD_ SQSYNTH      = 3 // square wave internal synth
MOD_ FMSYNTH      = 4 // FM internal synth
MOD_ MAPPER       = 5 // MIDI mapper
MOD_ WAVETABLE    = 6 // hardware wavetable synth
MOD_ SWSYNTH     = 7 // software synth

```

(Read only property)

**Voices as Integer**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Number of voices supported by an internal synthesizer device.

**Notes:**

If the device is a port, this member is not meaningful and is set to 0.  
(Read only property)

**Volume as Boolean**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Whether volume control is available.

**Notes:**

True if yes and False if no.  
(Read only property)

**VolumeStereo as Boolean**

property from class WindowsMidiOutputInfoMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Whether the device can control volume on two independent channels.

**Notes:**

True if stereo, False if mono.  
(Read only property)

### 3.10 class WindowsMidiMBS

#### class WindowsMidiMBS

class, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X:  
Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Windows Midi base class.

**Example:**

```
dim midi as WindowsMidiMBS // your midi object

Sub Open()
dim i as WindowsMidiInputInfoMBS
dim o as WindowsMidiOutputInfoMBS
dim c,n as integer

midi=new WindowsMidiMBS

c=midi.NumberOfMidiInputDevices-1

for n=0 to c
i=midi.InputDevice(n)

listbox1.AddRow str(n+1)
listbox1.Cell(listbox1.LastIndex,1)=i.Name
listbox1.Cell(listbox1.LastIndex,2)=hex(i.DriverVersion)

next

c=midi.NumberOfMidiOutputDevices-1

for n=0 to c
o=midi.OutputDevice(n)

listbox2.AddRow str(n+1)
listbox2.Cell(listbox2.LastIndex,1)=o.Name
listbox2.Cell(listbox2.LastIndex,2)=hex(o.DriverVersion)

next

End Sub
```

### 3.10.1 Methods

#### Connect(output as WindowsMidiOutputMBS)

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The Connect function connects a MIDI input device to a MIDI thru or output device, or connects a MIDI thru device to a MIDI output device.

**Notes:**

self must be a MIDI input device or a MIDI thru device.

output must be the MIDI output or thru device.

After calling this function, the MIDI input device receives event data in an DeviceData event whenever a message with the same event data is sent to the output device driver.

A thru driver is a special form of MIDI output driver. The system will allow only one MIDI output device to be connected to a MIDI input device, but multiple MIDI output devices can be connected to a MIDI thru device. Whenever the given MIDI input device receives event data in an DeviceData event, a message with the same event data is sent to the given output device driver (or through the thru driver to the output drivers).

Lasterror is set.

#### DataLost as integer

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Number of data blocks lost.

**Notes:**

The buffers in the plugins have a certain size.

In case midi events are coming fast in and the Idle method is not called often enough events are lost.

In that case increase the frequency of calling Idle or request the buffer size to be increased in the next plugin version.

**Disconnect(output as WindowsMidiOutputMBS)**

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The Disconnect function disconnects a MIDI input device from a MIDI thru or output device, or disconnects a MIDI thru device from a MIDI output device.

**Notes:**

self must be a MIDI input device or a MIDI thru device.

output must be the MIDI output device to be disconnected.

MIDI input, output, and thru devices can be connected by using the Connect function. Thereafter, whenever the MIDI input device receives event data in an DeviceData event, a message with the same event data is sent to the output device driver (or through the thru driver to the output drivers).

Lasterror is set.

**EventsLost as integer**

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Number of events lost.

**Notes:**

The buffers in the plugins have a certain size.

In case midi events are coming fast in and the Idle method is not called often enough events are lost.

In that case increase the frequency of calling Idle or request the buffer size to be increased in the next plugin version.

**Idle**

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Processes events.

**Notes:**

Midi events are buffered in data structures. This method dispatches them to the Realbasic event handlers. Call this method as often as you need events to fire. For example every 100ms in a timer.

### **InputDevice(index as integer) as WindowsMidiInputInfoMBS**

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The InputDevice function queries a specified MIDI input device to determine its capabilities.

**Example:**

```
dim midi as WindowsMidiMBS // your midi object
dim n,c as integer
dim i as WindowsMidiInputInfoMBS

c=midi.NumberOfMidiInputDevices-1

for n=0 to c
i=midi.InputDevice(n)

listbox1.AddRow str(n+1)
listbox1.Cell(listbox1.LastIndex,1)=i.Name
listbox1.Cell(listbox1.LastIndex,2)=hex(i.DriverVersion)

next
```

**Notes:** Index is from 0 to NumberOfMidiInputDevices-1.

### **NumberOfMidiInputDevices as integer**

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Returns the number of MIDI input devices present in the system.

**Example:**

```
dim midi as new WindowsMidiMBS
MsgBox str(midi.NumberOfMidiInputDevices)
```

**Notes:** A return value of zero means that there are no devices.

### NumberOfMidiOutputDevices as integer

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** Returns the number of MIDI output devices present in the system.

**Example:**

```
dim midi as new WindowsMidiMBS
MsgBox str(midi.NumberOfMidiOutputDevices)
```

**Notes:** A return value of zero means that there are no devices.

### OutputDevice(index as integer) as WindowsMidiOutputInfoMBS

method from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The OutputDevice function queries a specified MIDI output device to determine its capabilities.

**Example:**

```
dim midi as WindowsMidiMBS // your midi object
dim c,n as integer
dim o as WindowsMidiOutputInfoMBS

c=midi.NumberOfMidiOutputDevices-1

for n=0 to c
o=midi.OutputDevice(n)

listbox2.AddRow str(n+1)
listbox2.Cell(listbox2.LastIndex,1)=o.Name
listbox2.Cell(listbox2.LastIndex,2)=hex(o.DriverVersion)

next
```

**Notes:** Index is from 0 to NumberOfMidiOutputDevices-1.

### 3.10.2 Properties

#### Handle as Integer

property from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The handle for this Midi input or output port.

**Notes:**

Depending on which Realbasic class this is, value is a HMIDI, HMIDIIN or HMIDIOUT handle.  
(Read only property)

#### Lasterror as Integer

property from class WindowsMidiMBS, MIDI, MBS REALbasic Audio Plugin (WindowsMidi), Plugin version: 6.1, console safe, Mac OS X: Does nothing, Windows: Works, Linux x86: Does nothing.

**Function:** The last error code reported.

**Notes:**

0 is no error and -1 is parameter error from the plugin.  
(Read only property)



# Chapter 4

## List of all classes

• PortAudioDeviceInfoMBS	55
• PortAudioHostApiInfoMBS	40
• PortAudioHostErrorInfoMBS	31
• PortAudioMBS	32
• PortAudioStreamBaseMBS	43
• PortAudioStreamBufferedMBS	11
• PortAudioStreamInfoMBS	29
• PortAudioStreamMBS	22
• PortAudioStreamParametersMBS	53
• PortAudioStreamRecorderMBS	47
• PortMidiDeviceInfoMBS	71
• PortMidiEventMBS	78
• PortMidiMBS	72
• PortMidiStreamMBS	59
• WindowsMidiInputInfoMBS	98
• WindowsMidiInputMBS	93
• WindowsMidiMBS	104
• WindowsMidiOutputInfoMBS	100
• WindowsMidiOutputMBS	82
• WindowsMidiStreamMBS	88